



Steps to install E-Seek 260

1. Plug in the device (If plugged in for first time wait till drivers get auto install)
2. A valid Acuant Activation Code should be present
3. Acuant SDK 10.11.0406 (*released in 6368*) or higher version should be installed (as SDK 10.11.0406 supports new Acuant installer)
4. From the PassagePoint client application
 - Home - Station Preferences
 - Add Magnetic-stripe Readers - E-Seek Model 250 (will work for E-Seek 260 also)
 - Enter device name
 - Enter Valid Acuant 'Activation Code' > click Finish
5. Restart PassagePoint desktop client